

HF radar datasets to Shear current and Internal waves tasks

- Full library is located inside the synology server and another backup version in our github account "[HF_MEPLab_Codes](#)" under branch "giora".
- The code can be downloaded from github or directly run through the Synology path in case the server is mapped on the computer.
- The code was tested on Windows OS only, regarding Mac OS or Linux it has never been tried before - better to use it on Windows stations such as the XBand radar station or any personal computer which has Windows.
- The pipeline has been configured and changed throughout 3 years of collaborative work but it still might have flaws and errors. Any user of this library must approach this library with patience.
- Any additional change and improvements are more than welcomed and can be merge into the "main" branch on github via one of the collaborators
- To open the Python on the WERA lab station:
 - Open the terminal (konsol) and change directory to
"/home/wera/Documents/pycharm-community-2021.1.2/bin"
 - Once changed to this directory, insert: ./pycharm
 - Our pycharm projects are located in:
/home/wera/PycharmProjects/HandleSortFiles

Shear current - SORT files

Python operation

Preparing radial files - **working only on the WERA lab station**

Directory: `/home/wera/PycharmProjects/HandleSortFiles/WriteAngleFilesFromSort.py`

Outputs (on the synology server): `WERA/radials_spectrum/YYYYDDD/fname.asc`

```
if __name__ == '__main__':  
    station_id = 'is1' # is1: Ashkelon is2: Ashdod  
    year = '2021'  
    days_list = ['102'] # days to analyze  
    angles = np.arange(-3, 6, 1) # angles to calculate  
    basic_sort_path = '/mnt/synology/WERA/data/' + station_id + '/raw/' +  
    generate_day_deg(basic_sort_path, days_list, angles)
```

Changeable parameters:

- 1) Station_id: 'is1' or 'is2'
- 2) year: 'YYYY'
- 3) days_list: can be multiple days ['102', '103', '104']
- 4) angles: `np.arange(-3, 6, 1)` → -3 -2 -1 0 1 2 3 4 5 degrees.
 - a) Maximum angle: 60°, Minimum angle: -60°, Resolution: 1°

Without having the files from this script the following matlab pipeline will be crashed!

MATLAB operation:

Preparing the matlab matrix to faster post processing.

Directory: /WERA/MEPLab_HF_lib/radials_codes/Create_P_days.m

Outputs: /WERA/radials_spectrum/folderName

```
addpath(genpath('..\'));

%% generate full day mat file

Synology_path = 'Z:';
days = string({'2022039'});

%% point of interest

% ADCP implemented in front of
% Ashkelon May-June 2021
% ADCP_shallow = [34.532972 31.670556];
% ADCP_deep = [34.512833 31.681639];

% in_front_ASH = [34.58777539086895 31.854180076569225];
% in_situ = [34.4092 31.8135]; % Vector experiment February 8th 2022

%%

HF_station = 'is1'; % is1: Ashkelon, is2: Ashdod
N_range_cells = 1; % number of range cell to average
N_angs = 1; % number of angles to average (2*N_ang + 1)
```

Changeable parameters:

- 1) Synology path: Synology's WERA folder drive as mapped on the computer
 - 2) days: Days to analyze
 - a) **The .asc files of these days must be prepared using *WriteAngleFilesFromSort.py* to prevent script to crush**
 - 3) coordinate of interest: for example - In situ coordinate
 - 4) HF_Station: 'is1' or 'is2' to extract the spectrum from one of the stations
 - 5) N_range_cells: number of distances to average (usually 1)
 - 6) N_angs: number of angles to average over the coordinate of interest
- Example: For a target located 3.5 km off Ashkelon at angle 1 degree with 1 range cell average and 4 angles to average in each side the folder name would be:
is1_R_3.5622_Ncells_1_ang_-3_5
 - Inside this folder .mat files with information about the spectrum for every 20 minutes measurement will be stored
 - These matrices can be called for any case of post processing without the need to extract all the information from the HF radar

Analysis of the matrices generated by *create_P_day.m*

Directory: */WERA/MEPLab_HF_lib/radials_codes/Evaluate_U_from_P_day.m*

Outputs: time series plot of currents extracted from first order peaks and the accuracy

```

1  %% Calculate velocity values with optional averaging (average_every=3 e.c. 00:00-01:00, 01:00-02:00 etc.)
2
3  basic_path = 'Z:\radials_spectrum\isl_R_3.5622_Ncells_1_ang_-3_5\';
4
5  average_every = 3;
6  H = 72 / average_every;
7  dt = 24 / H ;
8
9  files = dir(basic_path);
10 files = files(3:16);
11
12 c0_all = -10.*ones(H*length(files), 3);
13 U_all = -10.*ones(H*length(files), 3); % [negative_peak, positive_peak, resolution]
14 eval_metric_all = -10.*ones(H*length(files), 4); % [sigma squared neg, sigma squared pos, acc neg, acc pos]
15 for cur_day = 1 : length(files)
16
17     id_zero = find(U_all == -10);
18     id_zero = id_zero(1);
19
20     cur_filename = strcat(basic_path, files(cur_day).name);
21     [cur_U_all, sig_metric, acc_metric, cur_c0] = get_U(cur_filename, average_every, '', 'centroid', 0.1);

```

Changeable parameters:

- 1) basic path - folder generated by *create_P_day.m*
 - a) If the folder wasn't generated before, the script will collapse!
- 2) average_every: number of sort files to average
- 3) files - which days inside the folder wants to be analyzed
- 4) After this - each section analyze the results (plot, fft, noise reduction)

Helper function: *get_U.m*

Inputs:

- 1) filename - specific .mat file representing 1 day measurement
- 2) Averaging parameter
- 3) Velocity type: 'Cp' to extract absolute velocity from both peaks " to extract current (deviation from undisturbed peak location)
- 4) Detection type: 'centroid', 'max' or 'WERA'
- 5) Optional: choose window size around highest peak (for centroid and WERA detection methods)
 - a) If empty a default value is used

Internal Waves

Python operation - must be executed serially

Preparing short sort files - **working only on the WERA lab station**

Directory: /home/wera/PycharmProjects/HandleSortFiles/generate_ShortSortFromSort.py

Outputs (Synology): /WERA/radials_spectrum_shortSort/ShortParamsFName/station/YYYYDDD

```
if __name__ == '__main__':  
  
    hours_dictionary = {0: '0000', 1: '0020', 2: '0040', 3: '0100', 4: '0120',  
                        8: '0240', 9: '0300', 10: '0320', 11: '0340', 12:  
                        16: '0520', 17: '0540', 18: '0600', 19: '0620', 20:  
                        24: '0800', 25: '0820', 26: '0840', 27: '0900', 28:  
                        32: '1040', 33: '1100', 34: '1120', 35: '1140', 36:  
                        40: '1320', 41: '1340', 42: '1400', 43: '1420', 44:  
                        48: '1600', 49: '1620', 50: '1640', 51: '1700', 52:  
                        56: '1840', 57: '1900', 58: '1920', 59: '1940', 60:  
                        64: '2120', 65: '2140', 66: '2200', 67: '2220', 68:  
  
    station_id = 'is1' # is1: Ashkelon is2: Ashdod  
    year = '2021'  
    days_list = ['102']  
    hours_list = np.arange(5, 10)  
  
    short_samples = '512'  
    shift_samples = '512'  
    range_cells = '50'
```

Changeable parameters:

- 1) station_id: 'is1' or 'is2'
- 2) year
- 3) days_list - can be multiple days ['102', '103', '104']
- 4) Hours_list - sort files to create the short Sort to them
- 5) Short Sort parameters
 - a) short_samples: length of each short sort: $N_{\text{samples}} * T_{\text{chirp}}$ ($T_{\text{chirp}} = 0.26\text{s}$)
 - b) shift_smamples: Number of samples to jump between consecutive samples - **only same value is applicable for future analysis**
 - c) range_cells: number of range cells to include ($N_{\text{cell}} = 50 \sim 25\text{km}$)

Prepare the radial files from the short sort files - **can be done only after the short sort generation**

Direction: `/home/wera/PycharmProjects/HandleSortFiles/WriteAnglesFilesFromShortSort.py`

Outputs (Synology): `/WERA/radials_spectrum_shortSort/ShortParamsFName/ST/YYYYDDD`

```
if __name__ == '__main__':  
    hours_dictionary = {0: '0000', 1: '0020', 2: '0040', 3: '0100', 4: '0120',  
                        8: '0240', 9: '0300', 10: '0320', 11: '0340', 12:  
                        16: '0520', 17: '0540', 18: '0600', 19: '0620', 20:  
                        24: '0800', 25: '0820', 26: '0840', 27: '0900', 28:  
                        32: '1040', 33: '1100', 34: '1120', 35: '1140', 36:  
                        40: '1320', 41: '1340', 42: '1400', 43: '1420', 44:  
                        48: '1600', 49: '1620', 50: '1640', 51: '1700', 52:  
                        56: '1840', 57: '1900', 58: '1920', 59: '1940', 60:  
                        64: '2120', 65: '2140', 66: '2200', 67: '2220', 68:  
                        72: '2400'}  
    # hours_list = np.arange(0, 72) # full day  
    year = '2021'  
    station_id = 'is1'  
    hours_list = np.arange(0, 10)  
    days_list = ['102'] # days to analyze  
    angles = np.arange(-3, 0, 1) # angles to calculate
```

Changeable parameters - **must have the same values generated by `generate_ShortSortFromSort.py`:**

- 1) station_id: 'is1' or 'is2'
 - 2) year
 - 3) days_list - can be multiple days ['102', '103', '104']
 - 4) Hours_list - sort files to create the short Sort to them
 - 5) Short Sort parameters
- Inside the YYYYDDD folder the .asc files are stored for later use
 - These are the same type of files as the .asc file of the SORT files but representing much shorter periods of time

MATLAB operation

Prepare .mat files that contain information of peak location for every time, distance and angle for later post processing use.

Directory: /WERA/MEPLab_HF_lib/radials_codes/operate_generate_internal_waves_mat.m

Outputs: /WERA/internal_waves/internal_waves_matrices

```
1 - addpath(genpath('..\'));
2
3 - Synology_path = 'Z:';
4
5 - ST = 'is1';
6 - cell_size = 512;
7 - step_size = 512;
8 - range = 50;
9 - distance = 40;
0 - angles = 1;
1 - day = '2021084';
2 - hhmm_start = char('0000');
3 - hhmm_end = char('0040');
```

Changeable parameters:

- 1) Synology path: Synology's WERA folder drive as mapped on the computer
 - 2) ST - ('is1' or 'is2')
 - 3) Cell_size, step_size, range
 - a) **All must be chosen according to already prepared .asc files**
 - 4) distance - which distance to insert into the final matrix
 - a) Must be lower than range
 - 5) angles - angles to insert into the final matrix
 - a) Angles between -angle to +angle are inserted
 - 6) Distance
 - 5) day - the day to analyze
 - a) must be chosen according to already prepared .asc files
 - 7) Hhmm start and end: specific hours within the day to analyze
 - a) '0000' and '2340' for whole day
- Final .mat file for further analysis is stored in the output folder

Shear current - Short SORT files

The python operation is the same described for internal waves

MATLAB operation:

Preparing the matlab matrix to faster post processing.

Directory: /WERA/MEPLab_HF_lib/radials_codes/Create_P_shortSort.m

Outputs: /WERA/radials_spectrum_shortSort/ShortParamsFName/ST/FolderName

```
addpath(genpath('..\'));

%% generate short sort mat file

Synology_path = 'Z:';
days = string({'2022039'});
short_params = "short_1024_shift_1024_range_100";
HF_station = 'isl'; %isl: Ashkelon, is2: Ashdod

hhms = string(...
    '0000', '0020', '0040', '0100', '0120', '0140', '0200',...
    '0220', '0240', '0300', '0320', '0340', '0400', '0420',...
    '0440', '0500', '0520', '0540', '0600', '0620', '0640',...
    '0700', '0720', '0740', '0800', '0820', '0840', '0900',...
    '0920', '0940', '1000', '1020', '1040', '1100', '1120',...
    '1140', '1200', '1220', '1240', '1300', '1320', '1340',...
    '1400', '1420', '1440', '1500', '1520', '1540', '1600',...
    '1620', '1640', '1700', '1720', '1740', '1800', '1820',...
    '1840', '1900', '1920', '1940', '2000', '2020', '2040',...
    '2100', '2120', '2140', '2200', '2220', '2240', '2300',...
    '2320', '2340');

splits = hhms(31:33);

%% coordinate of interest

%ADCP_shallow = [34.532972 31.670556];
%ADCP_deep = [34.512833 31.681639];
%in_front_ASH = [34.58777539086895 31.854180076569225];
in_situ = [34.4092 31.8135]; % February 8th, 2022 Vector, ADCP, Drone measurements

%%

N_range_cells = 1; % number of range cell to average
N_angs = 0; % number of angles to average (2*N_ang + 1)
```

Change to relevant values:

- 1) Synology path: Synology's WERA folder drive as mapped on the computer
- 2) days - the days to analyze
 - a) .asc files must be created before!
- 3) short_params - Short Sort parameter in the form of string as follows:
 - a) "short_<short_value>_short_<shift_value>_range_<range_cells_value>"
 - b) A folder with this values must be created from the previous python files
- 4) HF_station - 'is1' or 'is2'



- 5) splits - hours to analyze within each day
- 6) In situ - coordinate of interest
- 7) N_range_cells - Radial distances to average
- 8) N_angs - Azimuthal angles to average, the degree files must be ready from previous python file

Directory: /WERA/MEPLab_HF_lib/radials_codes/Evaluate_U_from_P_shortSort.m

Outputs: time series plot of currents extracted from first order peaks and the accuracy

```
%% Calculate current values from short Sort files (below the 20 minutes avg)

basic_path = 'Z:\radials_spectrum_shortSort\short_1024_shift_1024_range_100\is1\R_20.9184_Ncells_1_ang_22_22\';

average_every = 1;

T_chirp = 0.26; % chirp duration [seconds]
T_meas = 17.75; % duration of the full measurements [minutes]
short_samples = 1024; % must be equal to the hsort value of the path

num_splits = round(T_meas / (T_chirp * short_samples / 60));
H = num_splits / average_every;
dt = T_chirp * short_samples / 60;
```

Changeable parameters:

- 1) basic path - folder generated by *create_P_shortSort.m*
 - a) **If the folder wasn't generated before, the script will collapse!**
- 2) average_every: number of sort files to average
- 3) files - which days inside the folder wants to be analyzed
- 4) After this - each section analyze the results

Helper function: *get_U_shortSort.m* has the same features as *get_U.m*